

۱. ابتدا از منوی استارت عبارت Services را مطابق عکس زیر جستجو نماییدو بری روی آیکون آن کلیک کنید.





🔍 Services					- 0	×
File Action View	Halp					
🔍 Services (Local)	Services (Local)					
	Wired AutoConfig	Name	Description	Status	Startup Type	Log ^
		🥋 Windows Push Notification	This service	Running	Automatic	Loci
	Description:	Windows Push Notification	This service	Running	Automatic	Loci
	The Wired AutoConfig (DOT3SVC)	Windows PushToInstall Serv	Provides inf	-	Manual (Trig	Loci
	IEEE 802.1X authentication on	Windows Remote Manage	Windows R		Manual	Net
	Ethernet interfaces. If your current	Windows Search	Provides co	Running	Automatic (Loci
	wired network deployment enforces	🍓 Windows Security Service	Windows Se	Running	Manual	Loci
	802.1X authentication, the DO15VC service should be configured to run for establishing Layer 2 connectivity and/or providing access to network resources. Wired networks that do not enforce 802.1X authentication are	🖏 Windows Time	Maintains d	Running	Manual (Trig	Loci
		🏟 Windows Update	Enables the	Running	Automatic (T	Loci
		Windows Update Medic Ser	Enables rem		Manual	Loci
		WinHTTP Web Proxy Auto	WinHTTP i	Running	Manual	Loci
	unaffected by the DOT3SVC service.	Wired AutoConfig	The Wired A		Manual	Loci
		🔍 WLAN AutoConfig	The WLANS	Running	Automatic	Loci
		🔍 WMI Performance Adapter	Provides pe		Manual	Loci
		Work Folders	This service		Manual	Loci
		🍳 Workstation	Creates and	Running	Automatic	Net
		🎑 WWAN AutoConfig	This service		Manual	Loci
		🖏 Xbox Accessory Manageme	This service		Manual (Trig	Loci
		🎑 Xbox Live Auth Manager	Provides au		Manual	Loci
		🎑 Xbox Live Game Save	This service		Manual (Trig	Loci
		Abox Live Networking Service	This service		Manual	Loci
						~
		<				>
	Extended Standard					

۳. مطابق شکل زیر گزینه Startup type را بروری Automatic و بر روی گزینه Start کلیک میکنیم.

ene deserve	Log On	Recovery	Dependencies	
Service	name:	dot3svc		
Display	name:	Wired Auto	oConfig	
Descrip	tion:	The Wired responsible	AutoConfig (DOT3SVC) service is e for performing IEEE 802.1X stion on Ethemet interfaces. If your current	Ŷ
Path to	executabl	e:		
C:\Win	dows\syst	em32\svcho	st.exe -k LocalSystemNetworkRestricted +	P
Startup	type:	0. 4		
	up <u>⊆</u> .	Automatic	\$	~
Service	etatue:	Bunoing	<u> </u>	~
Service	status:	Running		<u>~</u>
Service	status:	Running	e <u>P</u> ause <u>R</u> esume	
Service Service	status: Start n specify t re.	Running Stop	<u>Bause</u> <u>Resume</u> ameters that apply when you start the service	×

۴. بعد از کلیک بر روی گزینه استارت مراحل مطابق شکل زیر پیش می رود

File Action View Help	Wired AutoConfig Properties (Local Computer)		
Services (Local) Wired Auto(Start the serv Description: The Wired Au service is resp IEEE 802.1X a Ethernet inte wired networ 802.1X authe service shoul for establishi and/or provi resources. W not enforce & unaffected b	General Log On Recovery Dependencies Service name: dot3svc Display name: Wired AutoConfig Service Control X Windows is attempting to start the following service on Local Computer P Wired AutoConfig Start Close Service status: Start Stop You can specify the start parameters that apply when you start the service from here. Start parameters:	of 74e ent) ×	Description This service r This service r This service f Provides infr Windows Re Provides cor Windows Sei Maintains da Enables the c Enables the c Enables remi WinHTTP im The WICA Ar The WLANSA Provides per This service s Creates and This service r This service r Provides aut This service r
	<		This service s

. در صورت انجام درست مراحل بالا پنجره ی زیر که مربوط به وارد کردن اطلاعات کاربری می باشد به نمایش در خواهد آمد .اطلاعات کاربری خود را وارد نمایید.

Services		- □ >
♦ ♦ 1 1 1 1 4 1 4 1 4 1 4 1 4 1 4 1 4 1		
Services (Local) Services (Local) Wired Aut Start the se Description The Wired, service is re IEEE 802.1X Ethernet in wired netw 802.1X aut service sho for establis and/or pro resources.	Wired AutoConfig Properties (Local Computer) General Log On Recovery Dependencies Service name: dot3svc Display name: Wired AutoConfig Service Control Windows Security Sign in User name Descrupted Descru	Description This service This service Provides int Windows R Provides co Windows S Maintains d Enables the Enables the WinHTTP in The Wired A
not enforce. unaffected	Password b Domain: OK Cancel	The WLANS Provides pe This service Creates and This service This service Provides au
	OK Cancel Apply	This service This service
Extended	Standard /	

<p۰. در صورت اتصال موفق ممكن است پيام زير به كاربر نمايش داده شود .بر ورى گزينه Connect كليلك نماييد.</p>

	nep	N	
		Wired AutoConfig Properties (Local Computer) X	
Services (Local)	O Service		
	Wired Auto(General Log On Recovery Dependencies	Description '
		Service name: dot3svc	This service r
	Stop the serv	6f	This service I
	restart the st	Lisplay name: Wired AutoConfig c74e	This service I
			Provides infr
	Description: The Wired Au	Ethernet authentication 2	Windows Re
service is res			Provides cor
	IEEE 802.1X a	Can't verify the server's identity	Windows Se
Ethernet inte wired networ			Maintains da
	802.1X authe		Enables the t
	service shoul	and connect. Continue connecting?	WinHTTP im
	and/or provi		The Wired A
	resources. W		The WLANS\
	not enforce &		Provides per
	unarrected b	▼ Details Connect Don't connect	This service s
			Creates and
		Start narametere:	This service r
			This service r
			Provides aut
		OK Cancel Apply	This service s
			This service s

۸. برای تنظیمات تکمیلی بر روی آیکون Network کلیک کنید.



۹. بر روی change Adaptor optiopn کلیک نمایید.



۱۰. بر روی کارت شبکه (معمولا با نام Ethernet) کلیک راست کرده و گزینه Properties را انتخاب می کنیم و بر روی تب Authentication



۰۱۱. در تب Authentication بر روی Setting کلیک نمایید



rotected EAP I	Properties			×
Vhen connectin	g:			
Verify the s	erver's ident	ity by validating	the certificat	e
				-
	o these serve	ers (examples:sr	v1;srv2;.~\.s	rv3\.com):
Trusted Root	Certification	Authorities:		
AAA Cert	ificate Servic	es		^
Actalis Au	Ithentication	Root CA		
Baltimore	CyberTrust I	Root		
	A rusted Netwo	ork CA		
Certum T	rusted Netwo	ork CA 2		
Class 3 P	ublic Primary	Certification Aut	thority	~
<				>
Notifications b	efore connec	ting:		
Tell user if the	server nam	e or root certific	ate isn't speci	fied 🗸
elect Authentic	ation Method	t:		
Secured passw	ord (EAP-MS	CHAP v2)	~	Configure
	Reconnect			
Disconnect if	server does	not present crv	ptobinding TL	v
Enable Ident	ity Privacy			
_				

۱۳. تیک گزینه Automatically use my windows logon name and password را بردارید.

Ethernet Properties	~
rotected EAP Properties	
EAP MSCHAPv2 Properties	<
When connecting:	a 113/ com).
Automatically use my Windows logon name and password (and domain if any).	v o peciniyi
OK Cancel	^
Actails Addrendcator Root CA Baltimore CyberTrust Root Certum CA Certum Trusted Network CA Certum Trusted Network CA 2 Class 3 Public Primary Certification Authority <	~
Notifications before connecting:	
Tell user if the server name or root certificate isn't spe	ecified ~
elect Authentication Method	
Secured password (EAP-MSCHAP v2)	Configure
Enable Fast Reconnect Disconnect if server does not present cryptobinding Enable Identity Privacy	π.v
ОК	Cancel

۱۴. برای تغییر گذرواژه یا ذخیره آن میتوان مطابق تصاویر زیر مراحل ۱ و ۲ را انجام دهید.

A disatisation of	802.1X settings
etworking Additionation Sharing	Specify authentication mode
Select this option to provide authenticated network access for this Ethemet adapter.	User authentication V Save credentials Delete credentials for all users
Choose a network authentication <u>m</u> ethod:	Enable single sign on for this network
Microsoft: Protected EAP (PEAP) ~ Settings	Perform immediately before user logon
	Perform immediately after user logon
Remember my credentials for this connection each	Maximum delay (seconds):
Ime images on ✓ Fallback to unauthorized network access	 Allow additional dialogs to be displayed during single sign on This network uses separate virtual LANs for machine
Additional Settings	and user authentication

۱۵. برای ذخیره گذرواژه تیک Remember my credentials for this را بزنید.

۱۶. درصورت اشتباه واردکردن اطلاعات کاربری، برروی کارت شبکه وضعیت زیر به نمایش درخواهد آمد.برای تغییر و یا اصلاح نام کاربری و رمز عبور میتوانید به گام ۱۴ برگردید.



۱۷. میتوانید مطابق تصاویر زیر با فعال و غیرفعال کردن کارت شبکه سیستم خود نسبت به احراز هویت مجدد و وارد کردن اطلاعات کاربری اقدام نمایید.

Network Connections



